

## Securitate si performanta

Incerari de introducere parola la autentificare inainte de deconectare

MaxLoginAttempts 3

Default este none cu sens de unlimited si seteaza nr. clientilor de la un IP care se pot conecta simultan. Atentie la NAT.  
Se poate folosi un mesaj indicat clientului la depasire. %m este maximum.

MaxClientsPerHost 2 "Too many (%m) from your IP"

Nr. maxim de clienti conectati cu acelasi username. Default none.

MaxClientsPerUser 1 "Only one such user at a time."

Nr. Maxim de conexiuni noi pe secunda acceptate pt. intreg serverul

MaxConnectionRate 2

Nr. maxim de conexiuni neautentificate per IP

MaxConnectionsPerHost 1 "Sorry, you may not connect !!"

The MaxHostsPerUser directive configures the maximum number of times different hosts, using a given login, can connect at any given time. The optional argument message may be used which will be displayed to a client attempting to exceed the maximum value. If message is not supplied, a default message of "Sorry, the maximum number of hosts (%m) for this user already connected

MaxHostsPerUser 2

The TimeoutNoTransfer directive configures the maximum number of seconds a client is allowed to spend connected, after authentication, without issuing a command which results in creating an active or passive data connection (i.e. sending/receiving a file, or receiving a directory listing).

TimeoutNoTransfer 300

Limitarea accesului la un director in functie de IP